#### Introduction to Network Address Translation

#### Network Infrastructure Workshop



These materials are licensed under the Creative Commons Attribution-NonCommercial 4.0 International license (<u>http://creativecommons.org/licenses/by-nc/4.0/</u>)



Last updated October 2019

This document is a result of work by the Network Startup Resource Center (NSRC at http://www.nsrc.org). This document may be freely copied, modified, and otherwise re-used on the condition that any re-use acknowledge the NSRC as the original source.



#### Network Address Translation

- NAT has become a commonly used technique for prolonging the use of IPv4 on today's Internet
  - Originally designed as a means of allowing isolated networks to connect to Internet without renumbering into public IP address space
- Presentation introduces NAT terminology, the typical use case in a Campus Network, and sample Cisco IOS configuration



#### **Network Address Translation**

- NAT is translation of one IP address into another IP address
- NAPT (Network Address & Port Translation) translates multiple IP addresses into one other IP address
  - TCP/UDP port distinguishes different packet flows
- NAT-PT (NAT Protocol Translation) is a particular technology which does protocol translation in addition to address translation
  - NAT-PT is has long been made obsolete by the IETF



## Carrier Grade NAT (CGN)

- Service Provider version of subscriber NAT
  - Subscriber NAT can handle only hundreds of translations
  - ISP NAT can handle millions of translations
  - Expensive high performance hardware
- Not limited to just translation within one address family, but does address family translation as well
- Sometimes referred to as Large Scale NAT (LSN)



### NAT Use Case

- A campus network does not have sufficient public IPv4 address space to address all the devices on their network
- Their service provider lets them use a small range of addresses e.g. /28
- The campus might divide the address space into two /29s
  - One /29 for services requiring public IP addresses
  - One /29 for translating internal addresses to public addresses



### NAT Use Case

- The /29 for public services:
  - Total of 8 addresses in the subnet
    - 1 address reserved for the gateway router
    - 2 addresses reserved for the subnet
    - 5 addresses available for servers & services
- The /29 for address translation:
  - Campus uses NAPT (network address and port translation) allowing mapping of multiple internal addresses to up to 8 external addresses



## How NAPT works

- NAPT allows mapping of multiple internal addresses to one external address.
  - Each TCP or UDP session is mapped to one TCP or UDP port of an external address
  - There are ~64000 unprivileged TCP and UDP ports
  - Typical end user device consumes ~400 TCP and UDP ports at any one time
  - Which allows around 150 end user devices per public IP address
- One /29 would allow only 1200 simultaneous fully active end user devices




## Squeezing more out of NAPT

- Network operators squeeze more internal users through NAPT devices by:
  - Reducing translation session timeouts
    - Cisco default for TCP is 24 hours!!
  - Reducing the number of TCP & UDP sessions any one internal user can have
    - Shows up as broken mapping applications
    - Shows up as "stuck internet"
    - Shows up as "sites unreachable"
  - Deploying IPv6 (!) which reduces the NAPT burden
    - Most large/popular content providers now support IPv6



#### Campus Use Case: Simple





# Typical Cisco configuration (1)

- NAT Configuration set up on Border Router
- Define the address range we want to NAT

ip access-list extended NATplus deny ip 100.64.10.0 0.0.0.255 any deny ip 192.168.0.0 0.0.255.255 192.168.0.0 0.0.255.255 permit ip 192.168.0.0 0.0.255.255 any deny ip any any log

- This says:
  - Don't NAT any of 100.64.10.0/24
  - Don't NAT when source and destination addresses are both internal
  - NAT internal source to any external destination
  - Anything that doesn't match is logged to catch "errors"



## **Typical Cisco configuration (2)**

• Define the external interface we want to NAT to:

```
interface GigabitEthernet 0/1
description Link to ISP
ip address 100.64.10.2 255.255.255.252
ip nat outside
```

• Define the internal interface we want to NAT from:

```
interface GigabitEthernet 0/2
description Link to Campus Core Switch
ip address 192.168.255.1 255.255.255.252
ip nat inside
'
```



## Typical Cisco configuration (3)

• Modifying the translation timeouts:

ip nat translation dns-timeout 60
ip nat translation icmp-timeout 180
ip nat translation udp-timeout 300
ip nat translation finrst-timeout 60
ip nat translation tcp-timeout 3600

- This will
  - Set the translation timeouts for DNS to 60 seconds, ICMP to 180 seconds, UDP to be 300 seconds, FIN/RST to be 60 seconds (all Cisco defaults), and TCP to 3600 seconds (from 86400 seconds default)
    - Timeout is when there is no more traffic using that mapping
  - Other translation timeout options are available in Cisco IOS too but the above are the most commonly used



## Typical Cisco configuration (4a)

• Activating the NAT on ONE IPv4 address

ip nat inside source list NATplus interface Gigabit 0/1 overload

- This will
  - match the NATplus list for traffic going from Gigabit 0/2 to Gigabit 0/1
  - Overload means use NAPT (one to many mapping using TCP/UDP ports)
    - NAPT will use the IP address of the Gigabit 0/1 port to map all the internal addresses to
- Campus traffic will appear as though it is all originated from the 100.64.10.2 address



# Typical Cisco configuration (4b)

- Activating the NAT on an IPv4 address pool
- First create the public address pool:

ip nat pool CAMPUS 100.64.10.64 100.64.10.67 prefix-length 29

- Which defines the pool CAMPUS having 4 IP public IP addresses out of the 100.64.10.64/28 address block given to the campus
- Now enable NAT

ip nat inside source list NATplus pool CAMPUS overload

- Which will match all traffic in the NATplus list translating it into the address pool CAMPUS




## Diagnosis on a Cisco Router

• To find out what is being translated:

Router# show ip nat translations					
Pro Inside global	Inside local	Outside local	Outside global		
udp 100.64.10.2:20480	192.168.0.65:20480	193.0.0.228:33436	193.0.0.228:33436		
udp 100.64.10.2:20482					
udp 100.64.10.2:20483	192.168.0.65:20483	192.36.148.17:334	36 192.36.148.17:33436		
udp 100.64.10.2:20484					
udp 100.64.10.2:20485					
udp 100.64.10.2:20486					
udp 100.64.10.2:20487	192.168.0.65:20487	192.228.79.201:33	436 192.228.79.201:33436		

- This shows
  - The local public IP address: UDP port
  - The local internal address and UDP port it maps to
  - And then the global destination addresses & ports







## Campus Use

• Campus 192.168.0.0/16 needs to be NAT'ed to different public IP addresses

HOPS AND CONFERENCE - 28 October 2021

• Assume that 100.64.10. Stud poet A NAT are used for the NAT pool – 8

addresses out of the 100.64.10.64/28 address block available

Function	Internal Subnet	External Address
Device Management & Internal Services	192.168.0.0/22	100.64.10.64
Science Faculty	192.168.16.0/20	100.64.10.65
Arts Faculty	192.168.32.0/20	100.64.10.66
Engineering Faculty	192.168.48.0/20	100.64.10.67
Library	192.168.64.0/20	100.64.10.68
Administration	192.168.96.0/20	100.64.10.69
Campus Wireless	192.168.128.0/17	100.64.10.70 & 100.64.10.71

### **Typical Cisco configuration (1)**

Define the address ranges we want to NAT

```
ip access-list extended Services-NAT
deny ip 100.64.10.0 0.0.0.255 any
permit ip 192.168.0.0 0.0.3.255 any
       ip any any
denv
ip access-list extended Science-NAT
deny ip 100.64.10.0 0.0.0.255 any
permit ip 192.168.16.0 0.0.15.255 any
deny
       ip any any
ip access-list extended Arts-NAT
deny ip 100.64.10.0 0.0.0.255 any
permit ip 192.168.32.0 0.0.15.255 any
deny
       ip any any
ip access-list extended Engineering-NAT
       ip 100.64.10.0 0.0.0.255 any
deny
permit ip 192.168.48.0 0.0.15.255 any
denv ip any any
```



## **Typical Cisco configuration (1)**

• Continued:

```
ip access-list extended Library-NAT
denv
       ip 100.64.10.0 0.0.0.255 any
permit ip 192.168.64.0 0.0.15.255 any
denv
       ip any any
ip access-list extended Admin-NAT
deny ip 100.64.10.0 0.0.0.255 any
permit ip 192.168.96.0 0.0.15.255 any
denv
       ip any any
ip access-list extended Wireless-NAT
       ip 100.64.10.0 0.0.0.255 any
denv
permit ip 192.168.128.0 0.0.127.255 any
deny ip any any
```

- Define one access-list per internally assigned address block



# Typical Cisco configuration (2)

- Internal and External interface NAT definitions are as in the previous example
- NAT translation timeouts also are as in the previous example



## Typical Cisco configuration (3)

• Now define the address pools:

ip nat pool	Services	100.64.10.64	100.64.10.64	prefix-length 29
ip nat pool	Science	100.64.10.65	100.64.10.65	prefix-length 29
ip nat pool	Arts	100.64.10.66	100.64.10.66	prefix-length 29
ip nat pool	Engineering	100.64.10.67	100.64.10.67	prefix-length 29
ip nat pool	Library	100.64.10.68	100.64.10.68	prefix-length 29
ip nat pool	Admin	100.64.10.69	.100.64.10.69	prefix-length 29
ip nat pool	Wireless	100.64.10.70	100.64.10.71	prefix-length 29

- Note that the public subnet we are NAT'ing into is 100.64.10.64/29
  - We can use all IP addresses in the /29
  - (The University's public servers use the other /29)



## Typical Cisco configuration (4)

• Now define the NAT function:

ip	nat	inside	source	list	Services-NAT	pool	Services overload
ip	nat	inside	source	list	Science-NAT	pool	Science overload
ip	nat	inside	source	list	Arts-NAT	pool	Arts overload
ip	nat	inside	source	list	Engineering-NAT	pool	Engineering overload
ip	nat	inside	source	list	Library-NAT	pool	Library overload
ip	nat	inside	source	list	Admin-NAT	pool	Admin overload
ip	nat	inside	source	list	Wireless-NAT	pool	Wireless overload

- This will match the internal address block with the correct external address
- The example shows how a more sophisticated NAT strategy could be developed for the campus



## Summary

- NAPT is useful technique for connecting large numbers of campus network devices to the public IPv4 Internet when the campus has limited or no public IPv4 address space
  - Private address space used for campus networks:
    - 10.0.0/8, 172.16.0.0/12, 192.168.0.0/16
- Border router is the most common location of the NAT device
  - Be aware of CPU loading though
- Be aware of NAT scaling limitations



#### Questions?



## Aside: NAT Issues (1)

- How to scale NAT performance for large networks?
  - Limiting tcp/udp ports per user harms user experience
  - Redesigning network
- Breaks the end-to-end model of IP
- Breaks end-to-end network security
- Breaks non-NAT friendly applications
  - Or NAT has to be upgraded (if possible)
- Content cannot be hosted behind a NAT



## Aside: NAT Issues (2)

- Makes fast rerouting and multihoming more difficult
  - Moving IPv4 address pools between CGNs for external traffic engineering
- Address sharing has reputation, reliability and security issues for end-users
- NAT device keeps the state of the connections
- Makes the NAT device a target for miscreants due to possible impact on large numbers of users



## Aside: NAT Issues (3)

- Consumer NAT device:
  - 5000 sessions means only 12 connected devices!
  - "NAT table FULL" error messages
  - "Broken Googlemaps"
  - "Stuck Internet"
- Carrier Grade NAT device:
  - 20 million sessions (Cisco ASR9001 ISM)
  - Which realistically is 50k users (400 sessions per user)
  - RIR 2x final IPv4 /22s only allows 640k users □

